



Home >> Documentation

>Motion - Table of contents

Methods

turn

walkStraight

walk

walkAroundBall

walkAroundBallInSteps

walkEndless

stopWalkDirectly

stopWalkSmoothly

Methods inherited from ALModule

exit

version

ping

getMethodList

getMethodHelp

getModuleHelp

wait

isRunning

stop

getBrokerName

getUsage

Overview Further Information

This is a Motion Module which takes care of all Motion concerning Robot Football, except Kicking the ball

Current version: 1.14

Warning

This doc is deprecated, please use the online Aldebaran documentation instead.

Methods

void turn (const float& thetaInDegrees)

Turnes by a angle in degrees

thetaInDegrees

The angle to turn

void walkStraight (const float& x)

Walks straight

x
distance in meters

void walk (const float& x, const float& y, const float& thetaInDegrees)

Walks to a coordinate with an angle theta

x x-coordinate y y-coordinate

thetaInDegrees thetaAngle

void walkAroundBall (const float& thetaInDegrees, const float& distanceToBall)

Walks around the ball with a distance

thetaInDegrees angle in degrees distanceToBall Distance to the Ball (15cm is a good estimate)

void walkAroundBallInSteps (const float& thetaInDegrees, const float& distanceToBall, const int& inSteps)

Walks around the ball with a distance in a certain amount of steps

thetaInDegrees
angle in degrees
distanceToBall
Distance to the Ball (15cm is a good estimate)
inSteps
Amount of Steps

void walkEndless (const float& thetaInDegrees, const float& speed)

Walks Endlessly with a given speed

thetaInDegrees angle in degrees speed The Speed

void stopWalkDirectly ()

Stops Directly

void stopWalkSmoothly ()

Stops Smoothly

Methods inherited from ALModule

void exit ()

Exits and unregisters the module.

string version ()

Returns the version of the module.

Returns

A string containing the version of the module.

bool ping ()

Just a ping. Always returns true

Returns

returns true

vector<string> getMethodList ()

Retrieves the module's method list.

Returns

An array of method names.

AL::ALValue **getMethodHelp** (const string& methodName)

Retrieves a method's description.

methodName

The name of the method.

Returns

A structure containing the method's description.

AL::ALValue getModuleHelp ()

Retrieves the module's description.

Returns

A structure describing the module.

bool wait (const int& id, const int& timeoutPeriod)

Wait for the end of a long running method that was called using 'post'

id

The ID of the method that was returned when calling the method using 'post'

timeoutPeriod

The timeout period in ms. To wait indefinately, use a timeoutPeriod of zero.

Returns

True if the timeout period terminated. False if the method returned.

bool isRunning (const int& id)

Returns true if the method is currently running.

Ьi

The ID of the method that was returned when calling the method using 'post'

Returns

True if the method is currently running

void stop (const int& id)

returns true if the method is currently running

hi

the ID of the method to wait for

string getBrokerName ()

Gets the name of the parent broker.

Returns

The name of the parent broker.

string getUsage (const string& name)

Gets the method usage string. This summarises how to use the method.

name

The name of the method.

Returns

A string that summarises the usage of the method.

Further Information

